


Focus Series 2026

Network License Settings



[1] Server Configuration


Installing Network License Server	-----	2p
Activating Network License	-----	4p

[2] Using Network License ----- 5p


[1] Server Configuration > Installing Network License Server

Preparing before installation

- * Configure the ZW3D network on the server PC and activate ZW3D network license.
- * Install ZW3D and Focus Series program on your PC.
- * Download the applicable version of the Focus Series Server Program.
(URL: <http://www.moldfocus.com/kor/download/>)




1. Run the **Focus Series Server Program** as administrator on the server PC.




2. Select a language, then click the **[OK]** button.


[1] Server Configuration > Installing Network License Server




3. Click the **[I Agree]** button.



4. Click the **[Next]** button.




5. Click the **[Install]** button.




6. When the installation is finished, click the **[Finish]** button.

[1] Server Configuration > Activating Network License




1. Run **FocusNetworkLIC.exe** in the [C:\ProgramData\ZWSOFT\ZWSOFT Network License Manager].




2. Click the **Save lcs file** button to save the *.lcs file on the desktop.

Send *.lcs file to the agency to receive Focus Series network license key.




3. Paste the **Focus Series network license key**(①) in the dialog.


When you click the **Activation**(②) button, the Success dialog appears.




4. Copy the **Server Name**, **IP** and **Access Number** to run the Focus Series.

[2] Using Network License




1. After running ZW3D, click the **Focus License Info**() icon on the Focus Series ribbon.




2. Select the **Network**(①) in the dialog.

Enter the **IP** (or Server Name) and **Access Number**(②) that you copied earlier, then click the **Activation**(③) button.



3. When the success message appears, click the **OK** button.



4. The product information is displayed when the network license is activated.

Note

If product information is not displayed, Focus Series is not available. Please check if there are any problems below.

- ZW3D network license disabled
- PC environments such as IP, port, etc. changed
- FocusNetworkLIC.exe removed by antivirus
- Failed to refer to License.log file
- Invalid server name/IP, access number
- Port is blocked by firewall
- FocusNetworkLIC.exe not running